

SMBプロトコル対応表

Samba	NT1(CIFS)	SMB1	SMB2	SMB2_02	SMB2_10	SMB2_22	SMB2_24	SMB3_00	SMB3_02	SMB3_10	SMB3_11
3.6	○	○	○	-	-	-	-	-	-	-	-
4.0	○	○	-	○	○	○	○	○	-	-	-
4.1	○	○	-	○	○	○	○	○	-	-	-
4.2	○	○	-	○	○	○	○	○	○	-	-
4.3	○	○	-	○	○	○	○	○	○	○	○
4.4	○	○	-	○	○	○	○	○	○	○	○
4.5	○	○	-	○	○	○	○	○	○	○	○
4.6	○	○	-	○	○	○	○	○	○	○	○
4.7	○	○	-	○	○	○	○	○	○	○	○
4.8	○	○	-	○	○	○	○	○	○	○	○
4.9	○	○	-	○	○	○	○	○	○	○	○
4.10	○	○	-	○	○	○	○	○	○	○	○
4.11	-	-	-	○	○	○	○	○	○	○	○
4.12	-	-	-	○	○	○	○	○	○	○	○
iX	NT1(CIFS)	SMB1	SMB2	SMB2_02	SMB2_10	SMB2_22	SMB2_24	SMB3_00	SMB3_02	SMB3_10	SMB3_11
V7.0up16(Samba3.6)	○	○	○	-	-	-	-	-	-	-	-
V7.0up54(Samba3.6)	○	○	○	-	-	-	-	-	-	-	-
V7.0up57(Samba3.6)	○	○	○	-	-	-	-	-	-	-	-
V7.0up60(Samba4.6)	○	○	-	○	○	○	○	○	○	○	○
V7.0up65(Samba4.6)	○	○	-	○	○	○	○	○	○	○	○
V7.0up66(Samba4.6)	○	○	-	○	○	○	○	○	○	○	○
Windows OS	NT1(CIFS)	SMB1	SMB2	SMB2_02	SMB2_10	SMB2_22	SMB2_24	SMB3_00	SMB3_02	SMB3_10	SMB3_11
Windows 2000 pro	○	○	-	-	-	-	-	-	-	-	-
Windows XP	○	○	-	-	-	-	-	-	-	-	-
Windows Vista	○	○	○	-	-	-	-	-	-	-	-
Windows Vista SP1	○	○	○	○	-	-	-	-	-	-	-
Windows 7	○	○	○	○	○	-	-	-	-	-	-
Windows 8 ベータ版 初期	○	○	○	○	○	○	-	-	-	-	-
Windows 8 ベータ版	○	○	○	○	○	○	○	-	-	-	-
Windows 8	○	○	○	○	○	○	○	○	-	-	-
Windows 8.1	○	○	○	○	○	○	○	○	○	-	-
Windows 10 初期	○	○	○	○	○	○	○	○	○	○	-
Windows 10 現行	-	-	○	○	○	○	○	○	○	○	○
Windows Server OS	NT1(CIFS)	SMB1	SMB2	SMB2_02	SMB2_10	SMB2_22	SMB2_24	SMB3_00	SMB3_02	SMB3_10	SMB3_11
Windows 2000 Server	○	○	-	-	-	-	-	-	-	-	-
Windows Server 2003	○	○	-	-	-	-	-	-	-	-	-
Windows Server 2003 R2	○	○	-	-	-	-	-	-	-	-	-
Windows Server 2008	○	○	○	-	-	-	-	-	-	-	-
Windows Server 2008 R2	○	○	○	○	○	-	-	-	-	-	-
Windows Server 2012	○	○	○	○	○	○	○	○	-	-	-
Windows Server 2012 R2	○	○	○	○	○	○	○	○	○	-	-
Windows Server 2016	○	○	○	○	○	○	○	○	○	○	○
Windows Server 2019	-	-	○	○	○	○	○	○	○	○	○